Update RAK WisBlock modules in PlatformIO platforms and packages

After updating the Adafruit nRF52, Espressif ESP32 or Arduino Mbed package do the following steps:

- 1 Open a project that uses the updated platform
- 2 Compile the project so that PlatformIO is installing the packages belonging to the platform

Ignore the "*Unknown board ID*" or "*variant.h*: *No such file or directory*" errors until the following patch has been applied

3 Patch the platform and package:


A Unzip the contents of *RAK_PATCH.zip* into folder *RAK_PATCH* in your PlatformIO installation folder.

Paths on different OS:

Windows: %USER%\.platformio\
Linux: ~/.platformio/

Mac OS: /Users/{Your_User_id}/.platformio/

Example (Windows 10):



B Install the patch

Open a terminal in the .platformio folder and execute python ./rak_patch.py

Example (Windows 10 terminal):

```
Microsoft Windows [Version 10.0.19042.1165]
(c) Microsoft Corporation. All rights reserved.

C:\Users\RAKwireless>cd C:\Users\RAKwireless\.platformio\RAK_PATCH

C:\Users\RAKwireless\.platformio\RAK_PATCH>python rak_patch.py

Patched RAK4631

Patched RAK11200

Patched RAK11310

Patch done, check output if successful

C:\Users\RAKwireless\.platformio\RAK_PATCH>_
```

Example (Linux):

```
MINGW64:/c/Users/RAKwireless/.platformio/RAK_PATCH

RAKwireless@RAK-BeeGee MINGW64 ~/.platformio/RAK_PATCH

Spython ./rak_patch.py
Patched RAK4631
Patched RAK11200
Patched RAK11310
Patch done, check output if successful

RAKwireless@RAK-BeeGee MINGW64 ~/.platformio/RAK_PATCH

$
```